



Unity Agent Help Guide

# UNITY AGENT HELP GUIDE

---

## CONTENTS

<b>1</b>	<b>About Unity Agent .....</b>	<b>7</b>
1.1	Naming Conventions for this Help .....	7
1.2	System Requirements .....	7
1.2.1	Windows PC Requirements .....	7
1.2.2	Internet & Firewall .....	8
<b>2</b>	<b>Initial Setup.....</b>	<b>8</b>
2.1	Call Center Login Details .....	9
2.2	Call Center Login Default Password.....	10
2.3	Selecting a Pre-Configured Template .....	11
2.4	Manual and Auto Updates .....	11
2.5	Rollback available .....	12
<b>3</b>	<b>Unity Agent Interface Overview .....</b>	<b>12</b>
3.1	Resizing Unity Agent .....	13
3.2	Maximizing and Minimizing .....	13
3.3	Using Unity Agent from the System Tray.....	14
3.4	Call Notification Preferences .....	14
3.4.1	Show Remote Party Phone Number .....	15
3.4.2	Override Contact Name Using Number .....	15
3.5	Summary Toast Notification .....	15
3.6	Browser Screen-Pop .....	15
3.7	Appearance.....	16
3.8	Skins.....	16
<b>4</b>	<b>Main Interface Elements .....</b>	<b>16</b>
4.1	ACD State Buttons .....	16
4.2	Call Control .....	16
4.3	Active Call Window .....	17
4.4	Contacts [Busy Lamp Field].....	17
4.5	Call Logs .....	17
4.6	Voicemail .....	17

<b>5</b>	<b>Call Center Agent Functionality .....</b>	<b>18</b>
5.1	Changing ACD State .....	18
5.1.1	Only Show One ACD Button .....	19
5.1.2	Assigning Unavailable Codes .....	19
5.1.3	Force Disposition Code .....	20
5.1.4	Displaying ACD State Duration.....	20
5.2	Using Personal Wallboard.....	21
5.2.1	Locking in Minimized State .....	21
5.2.2	Configuring Statistics Columns in Personal Wallboard .....	22
5.2.3	Customizing Statistics Label .....	22
5.2.4	Configuring Alert Thresholds in Personal Wallboard .....	23
5.3	Joining & Leaving Queues .....	24
5.4	Receiving ACD Calls.....	24
5.5	Using Disposition Codes.....	24
5.6	Auto Answer .....	25
5.7	Supervisor Escalation.....	26
5.7.1	Standard Escalation .....	26
5.7.2	Emergency Escalation .....	26
5.7.3	Escalation via Active Call Window .....	27
5.7.4	Escalation via Personal Wallboard.....	27
5.8	Activating Outbound DNIS .....	28
5.9	Personal Statistical Reports .....	28
5.10	Pre-configuration of ACD State.....	29
<b>6</b>	<b>Call Control .....</b>	<b>30</b>
6.1	Making a Call.....	30
6.1.1	Using the Dial Window .....	30
6.1.2	Using the Contacts Panel .....	30
6.1.3	Drag and Drop.....	30
6.1.4	Using Directory Search.....	31
6.1.4	Dialing from the clipboard .....	31
6.2	Answer a Call .....	31
6.3	End a Call .....	31
6.3	Redial .....	31
6.4	Send Call to Voicemail .....	32
6.4.1	Retrieving Voicemail Messages via VoiceMail Button .....	32
6.4.2	Retrieving Voicemail Messages via Voicemail tab .....	32
6.5	Transferring a Call.....	32
6.5.1	Announced Transfer .....	33

6.5.1.1	Warm Transfer.....	33
6.5.2	Blind Transfer.....	34
6.5.2.1	Using Contacts Panel Drag and Drop .....	34
6.5.2.2	Using Transfer Button.....	34
6.5.2.3	Using Right Click.....	34
6.5.3	Transfer to Voicemail.....	35
6.5.3.1	Using Contacts Panel Right Click - Voicemail .....	35
6.5.3.2	Using Drag and Drop.....	35
6.5.4	Transfer to Mobile .....	35
6.5.4.1	Using Contacts Panel Right Click - Mobile.....	36
6.5.4.2	Using Drag and Drop.....	36
6.6	Call Hold/Retrieve.....	36
6.6.1	Placing a Call on Hold.....	36
6.6.2	Retrieving a Held Call .....	36
6.7	Conference Calling.....	36
6.7.1	Starting a Conference Call.....	37
6.7.2	Ending a Conference Call .....	37
<b>7</b>	<b>Active Call Window .....</b>	<b>37</b>
7.1	Window Layout.....	38
	Calls In Queue .....	38
7.2	Managing Multiple Calls .....	38
7.3	Resizing the Active Call Window.....	38
7.4	Assigning an Account Code.....	39
<b>8</b>	<b>Drag and Drop .....</b>	<b>39</b>
8.1	Make a Call to a User or Number.....	40
8.2	Transferring a Call to a User .....	40
8.3	Make a Call to a Call Center Queue .....	40
8.4	Transferring a Call to a Call Center Queue.....	40
8.5	Send to Voicemail .....	40
8.6	Call Control .....	40
8.7	Send New Instant Message.....	40
8.7.1	Add Participant to Existing IM Session.....	41
8.7.2	Transfer Call to IM Participant .....	42
<b>9</b>	<b>Contacts Panel [Busy Lamp Field] .....</b>	<b>42</b>
9.1	Contact Panel Display Options.....	42
9.1.1	Details View .....	43
9.1.2	List View.....	43
9.1.3	Small Icon View.....	44

9.1.4	Tile View .....	44
9.2	User Icons .....	44
9.2.1	User Icon Engaged Tool Tip.....	45
9.2.2	Instant Messaging Availability .....	45
9.3	Managing Monitored Users in the Contacts Panel .....	45
9.5	Performing Call Control Actions in the Contacts Panel.....	46
9.5.1	Call Extension.....	46
9.5.2	Answer This Call [Call Pick-Up].....	46
9.5.3	Park Call on Extension.....	47
9.5.3.1	Retrieving Parked Calls .....	47
9.5.4	Camp Call on Extension .....	47
9.5.6	Call Mobile .....	48
9.5.7	Transfer Call to Mobile .....	48
9.5.8	Transfer Call to VoiceMail.....	48
9.5.9	Barge into This Call .....	48
9.5.10	Call Extension When Available.....	49
9.5.11	View User Details .....	49
9.5.11.1	Adding Audio Alerts to Monitored Users.....	50
9.5.12	Send Email .....	50
9.5.13	Answer This Call [Call Pick-Up].....	50
<b>10.</b>	<b>Instant Messaging .....</b>	<b>51</b>
10.1	Online/Offline Indicator.....	51
10.2	Docking the IM Window .....	51
10.3	Undocking and Redocking IM sessions .....	52
10.4	Sending an Instant Message .....	53
10.5	Overview of IM Window .....	53
10.6	Adding Participants to an Existing IM Session .....	54
10.7	Sending Contact Directory Numbers .....	54
10.8	IM Notification Settings .....	55
10.9	Send IMs to Offline Users .....	55
10.9.1	Logging IM Sessions .....	55
10.10	XMPP Integration.....	56
10.10.1	XMPP Authentication.....	56
10.10.2	Managing XMPP Subscriptions .....	57
10.10.3	Instant Message Priority .....	59
10.10.4	Configuration .....	59
<b>11</b>	<b>Personal Directory .....</b>	<b>60</b>
11.1	Add New Entry.....	60

11.2	Edit Entry .....	61
11.3	Remove Entry.....	61
11.4	Dialing Directory Entry.....	61
11.5	Import Personal Directory .....	62
11.6	Export Personal Directory.....	62
<b>12</b>	<b>Contact Search Directories .....</b>	<b>63</b>
12.1	Loading Directories .....	63
12.2	Contact Search Results Layout.....	63
12.3	Contact Search Settings .....	64
12.3.1	Listing Directories .....	64
12.4	Configuring Outlook Contacts Preferences.....	65
12.5	Third Party Directories .....	65
12.6	Desktop Integration.....	66
<b>13</b>	<b>Call Logs.....</b>	<b>66</b>

## 1 ABOUT UNITY AGENT

---

Unity Agent is a Microsoft® Windows® based application that provides a fully integrated hosted telephony environment, including allowing the user to join/leave call center queues to which they are assigned, change their ACD state and view personal and overall call center statistics and queue conditions.

### 1.1 Naming Conventions for this Help

- a. Call Center instances are also referred to as Queues in this guide
- b. ACD calls mean incoming calls into the call center/queue
- c. BWKS means the BroadSoft BroadWorks platform

### 1.2 System Requirements

#### 1.2.1 Windows PC Requirements

- a. Unity will require approx 20MB of hard drive space on the local machine
- b. By default the install directory is C:\Program Files (x86)\Unity Client
- c. Minimum computer spec: CPU: dual core 3Ghz. Ram: 4GB. Video Card: 256MB onboard RAM. As a general note, the requirements to run Unity Agent are considerably less than

those required to run Windows

- d. Unity can be rolled out as an MSI file, which supports Active Directory group profiles

- e. Unity is only supported on Windows 7, Windows 8.1 and Windows 10
- f. Both 32 and 64-bit versions of Windows are supported. There are no special permissions required to install Unity

### 1.2.2 Internet & Firewall

Unity requires high-speed internet connectivity and access to the below locations, which may require firewall rules to be added on the customer premises:

- a. TCP port 2208 to im.unityclient.com
- b. TCP port 2208 to the VoIP platform OCI server
- c. HTTP/HTTPS access to portal.unityclient.com
- d. HTTP/HTTPS access to the VoIP platform XSI server [if call recording, visual voicemail or enhanced call center reports are used]

## 2 INITIAL SETUP

---

The first-time Unity is started you will be prompted to enter the configuration details, as shown below. Unity can then retain the connection and authentication details for later use. The Login ID and Password will be assigned from your Service Provider.



The screenshot shows a web form titled "Broadworks Login Details". It contains two text input fields: "Login ID" and "Password". Below these fields are two checkboxes, both of which are checked: "Remember my login ID" and "Remember my password".

Next you will be prompted for the server address for your Service Provider. If this field is already populated do not change it. In most cases you can leave the Server Port as 2208. Leave the Unity Server Connection Details as those prefilled.

**Broadworks Server Connection Details**

Server address

Server port

**Unity Server Connection Details**

Server address:


Server port:

☐ Log connections

Restart Unity Agent to begin.

## 2.1 Call Center Login Details

Once Unity has been restarted it will connect to the host BroadWorks system and populate all the Call Center Instance IDs for the call centers that the agent is a member of as shown below.



The password for each call center must be added in order to populate the call centers in the Personal Wallboard. Double click a call center to add the password. Where the password is the same for each call center click the “Apply to all queues without a password” box and restart. Unity will now login as the call center queues and you will see these begin to populate the Personal Wallboard.

**Call Center Login Details**


Service ID  
boltssales@drd.co.uk

Password  
[ ]

Login status  
The password has not been entered.


☐ Apply to all queues without a password

Ticking “Alert me when a call center login fails” will pop this dialogue box when Agent starts and cannot login successfully to a call center.




## 2.2 Call Center Login Default Password

If all call center passwords are the same, use the default password option. Enter the password for the call centers so that when a new call center is added in the future the agent doesn't have to enter the call center password as Unity will do this automatically. Please note that all call center passwords have to be the same for this option to work.




## 2.3 Selecting a Pre-Configured Template

User templates can only be created by an administrator to configure default settings for agents. ACD buttons, call center control, recording options and all other settings can be configured and saved as a template that can be easily assigned to all users. Please see your Administrator for a separate guide on using Unity Templates.



## 2.4 Manual and Auto Updates

Unity can be configured to automatically update when a new version is available. Simply tick the box in settings>update as shown below.




When a new version of Unity is available the user will be presented with a popup asking to restart Unity. Once Unity has restarted the latest version will be running. You can also configure how often Unity looks for updates under the auto update box. To manually update Unity, click Perform manual update now and Unity will search for any new updates.




## 2.5 Rollback available

If rollback available is ticked in the Unity portal, then users can rollback to previous versions of Unity. Go to settings>update and then choose the desired version from the drop-down menu.



Once you've selected which version you want to rollback to click the green tick and the box below will appear.




Click Yes and then click Ok.

## 3 UNITY AGENT INTERFACE OVERVIEW

---


Unity is split into six functional areas; ACD Buttons, Call Control buttons, Personal Wallboard, Active Call Window, Contacts [Busy Lamp Field and Instant Messages]. Contacts is a tab that can be toggled to display Call Logs, Abandoned Calls and the Voicemail tab.




### 3.1 Resizing Unity Agent

Unity can be dragged from any corner to the required size. The Active Call Window resizes independently by dragging the border at the bottom of the list [where the lower red line is in the illustration above]. When Unity is closed, all current dimensions will be saved.


### 3.2 Maximizing and Minimizing


Unity can be maximized and minimized using the standard buttons in the top right-hand corner of the application. When minimized, Unity appears in the system tray in the bottom right hand corner of the desktop where the Unity icon  will be displayed. To re-open Unity simply double click this icon, or right click and select Restore from the menu, as shown below.




### 3.3 Using Unity Agent from the System Tray


In its minimized state, Unity Agent can be configured to sit in the System Tray. This is in Settings [button] > Settings [tab] Appearance.



Right clicking the Unity icon  in the system tray allows the user to dial or redial, configure settings such as CommPilot Express Profiles, DND, Call Forward Always or Remote Office, or change their ACD state. Note: Only those services that are assigned to the user in BroadWorks will be displayed.




Selecting “Call number” will provide a list of the last 10 dialed numbers as illustrated below. “New number” will pop a call box where the user enters the desired number using their computer keyboard.



### 3.4 Call Notification Preferences

Unity Agent can be configured to pop when a call is presented or pop a “toast” summary notification above the system tray when a call is presented. Optionally, Agent can also perform auto-answer when using click-to-dial. If this is not selected, then the IP phone will ring and the user will have to lift the handset to initiate the outbound call.



### 3.4.1 Show Remote Party Phone Number

This setting will configure to show the remote party number [if available], as shown below. This applies to both internal and external parties.

From	To	Duration	Status
Chris Tutt	Andrew Smith (0002)	00:00	Ringing

### 3.4.2 Override Contact Name Using Number

Unity can also perform a contact search based on the remote party number even if the name was provided by the Broadworks platform, this is especially useful when the name delivered through the PSTN is incorrect, for example in some cases this may always be “WIRELESS CALLER”.

## 3.5 Summary Toast Notification

The summary notification is presented for hunt group, ACD and DID calls and can be used to route the call to voicemail or answer the call.




## 3.6 Browser Screen-Pop

The summary notification is also clickable and can be used to open the PC default browser to a preconfigured URL and append incoming call information, such as the phone number of the remote party. This feature can be used for screen popping CRM systems and other browser based applications. Further information on this feature is in a supplementary guide.


### 3.7 Appearance

In Settings [button] > Settings [tab] > Appearance, the user can change the behavior of Unity.



**Always show on top of all windows** – Unity will always be on top


**Show missed call count in the call log tab** – When enabled Unity will provide a count of the number of missed calls as below



**Show remote party phone number** – This will show the phone number and the name [if matched] in the “From” field

### 3.8 Skins

In Settings [button] > Settings [tab] > Appearance > Skin, the user can change the look of Unity with preset Skins.



## 4 MAIN INTERFACE ELEMENTS

### 4.1 ACD State Buttons

ACD State buttons for setting the agent's availability to the call center. When clicking “Unavailable” the user will be presented a list of unavailable codes as configured in BroadWorks.

### 4.2 Call Control

Call Control buttons provide quick access to common telephone handling commands. Only services that are assigned to the user are displayed. For example, if Call Recording and Voicemail are not assigned then the buttons will not be displayed.

### 4.3 Active Call Window

This provides a list of all current calls and their state. For example, Ringing, Active or On Hold. The duration of the call is also displayed. This is from the moment the call was first placed and does not reset when a call is Held or Retrieved. Unity will mirror any call handling made on the user's IP phone. For example, if the call is placed on Hold on the handset, the user will show as being on Hold in the Active Call Window.

### 4.4 Contacts [Busy Lamp Field]

This panel will display up to 30 monitored users, displaying their Do Not Disturb [grey], Available [green], Engaged [red] or Ringing [orange] state as icons.

### 4.5 Call Logs


Toggling the bottom Contacts panel to Call Logs will display Missed Calls, Received Calls and Dialed Calls. Missed Calls will include both direct inward DID calls, ACD and Hunt Group calls. 20 numbers can be stored unless the user has Enhanced Call Logs service assigned.

Call Logs can also be cleared, reloaded or exported with the icons at top right of the panel.




### 4.6 Voicemail

Clicking into the Voicemail tab will display a list of voice messages with the most recent at the top. Double click an entry to play through the PC's default media player. Right click to save locally or delete.



In order for the Voicemail tab to appear, Agent must be configured for “Use unified messaging” and “Show visual voicemail tab” in Voicemail settings as below.



## 5 CALL CENTER AGENT FUNCTIONALITY


### 5.1 Changing ACD State

Clicking Unavailable, Available or Wrap-Up will change your availability for all queues you are a member of. This will not impact receiving inbound direct calls. The currently selected state will have the ACD state name in red text, as Available is in the below example.




### 5.1.1 Only Show One ACD Button

Unity Agent can optionally be configured in Settings > Incoming Calls > Call Center > Agent > ACD State to only display one ACD button, which will be the currently selected state. Left clicking will provide the other ACD options.




### 5.1.2 Assigning Unavailable Codes

When the agent selects unavailable, any unavailable codes that have been configured in BroadWorks will appear. Unavailable Code assignment with one ACD button:





Unavailable Code assignment with three ACD buttons:



### 5.1.3 Force Disposition Code

To assign a Disposition Code the agent right clicks in the Active Call Window. Unity can force the agent to enter a disposition code by setting their ACD state post-call to Wrap-Up ACD state. When Unity is configured to force the agent to assign a disposition code through a popup window which is automatically displayed to the user when the call is released.

The Unity UI will be disabled and the popup window will appear over all applications on the user's desktop. A timer can be specified which will display a count-down to the user, and will automatically close once the timer duration has elapsed. When they click Available they get a drop list of Disposition Codes. They must choose one for the previous call before they can become Available. This feature is activated in Settings as below.




### 5.1.4 Displaying ACD State Duration


The top bar in Unity Agent will show the current ACD state as below.

Unity Agent: Jenna Wimshurst - Unavailable - Comfort Break (duration: 00:08)

This can optionally be configured to also display the ACD duration or the time that the ACD state was changed. This is configured in Settings > Agent > ACD State as below.



## 5.2 Using Personal Wallboard

The Personal Wallboard will show current performance metrics for the call centers the agent is assigned to. The stats are broken down by “My Statistics” which shows the agent's individual performance and “Overall Queue Statistics” which will show the current conditions across the entire call center[s]. The  icon at the upper right hand corner of Personal Wallboard toggles between showing all call centers individually [maximized view] or a summary of all call centers combined [minimized view].

### Maximized View

My Statistics										Overall Queue Statistics									
Name	Total Calls	Web Chats Answered	Answered Calls	Total Talk Time	Missed Calls	Average Talk Time	Emails Answered	Web Chats Receive		Total Calls	Calls Answered	Total Missed Calls	Calls In Queue	Longest Wait Time	Average Wait Time	Average Talk Time	Calls Abandoned	Web Chats Queued	Web Chats Answered
Kakapo Systems	-	0	-	-	-	-	0	0	-	-	-	-	-	-	-	-	-	0	3
Bolts Sales	0	0	0	00:00	0	00:00	0	0	0	0	0	0	0	00:00	00:00	00:00	0	0	0
Nuts Sales	0	-	0	00:00	0	00:00	-	-	0	0	0	0	0	00:00	00:00	00:00	0	-	-
	0	0	0	00:00:00	0	00:00	0	0	0	0	0	0	0	00:00	00:00	00:00	0	0	3


### Minimized View

My Statistics										Overall Queue Statistics									
Name	Total Calls	Web Chats Answered	Answered Calls	Total Talk Time	Missed Calls	Average Talk Time	Emails Answered	Web Chats Receive		Total Calls	Calls Answered	Total Missed Calls	Calls In Queue	Longest Wait Time	Average Wait Time	Average Talk Time	Calls Abandoned	Web Chats Queued	Web Chats Answered
Summary	0	0	0	00:00:00	0	00:00	0	0	0	0	0	0	0	00:00	00:00	00:00	0	0	3

Note: Statistics shown in Personal Wallboard reset every 24 hours at midnight.

### 5.2.1 Locking in Minimized State


To disable the ability to maximize and minimize the Personal Wallboard, activate “Only display summary statistics” in Settings > Call Center > Statistics as below.



## 5.2.2 Configuring Statistics Columns in Personal Wallboard

The statistics shown in “My Statistics” and “Overall Queue Statistics” panels of the Personal Wallboard are configurable in Settings > Services > Call Center > Statistics > Columns.

Statistics can be added or removed with the   buttons and the order they are displayed, from left to right in the Personal Wallboard can be changed with the arrows. Topmost is to the left.



## 5.2.3 Customizing Statistics Label

Double click any statistic as displayed in the list above. From the below field you are able to customize the statistic label as required.

Statistic to display  
 NumberOfCallsAbandoned

Column heading  
 Abandoned

☒ Set threshold alert values

☒ Highlight non-zero values

☒ Increasing thresholds (calls)

Green: >= 1

Yellow: >= 2

Red: >= 5

Black: >= 10

Selecting “Highlight non-zero values” will cause any value over 0 to be displayed in red. This has been activated for the “Total Calls” statistic below.

Overall Queue Statistics		
Total Calls	Calls Answered	Total Missed Calls
0	0	0
0	0	0
6	6	0
6	6	0

## 5.2.4 Configuring Alert Thresholds in Personal Wallboard

Double click any Statistic in Settings > Services > Call center > Statistics > Columns and tick “Set threshold alert values”. This will display a table where corresponding values can be configured that will progressively change the statistic background color green, yellow, red and black.

Some statistics allow a different threshold to be set per call center, for example important queues can have lower thresholds.

Services & Settings

Services Settings

Incoming Calls

- Anonymous Call Rejection
- Call Forward Always
- Call Forward Busy
- Call Forward No Answer

Call Center

- Agent
- ACD State
- Statistics
- Columns
- Reporting
- Abandoned Calls
- Comm Plot Express
- Available: In Office
- Available: Out Of Office
- Busy
- Unavailable
- Do Not Disturb
- External Calling Line ID Delivery
- Internal Calling Line ID Delivery
- Simultaneous Ring

Outgoing Calls

- Calling Line ID Delivery Blocking

Call Control

- Broadworks Anywhere
- Broadworks Mobility
- Call Transfer
- Call Park Retrieve
- Call Recording
- Call Waiting

Specify which columns should be displayed in the personal wallboard. Threshold values can also be set for many columns

Statistic to display  
 NumberOfCallsAbandoned

Column heading  
 Abandoned

☒ Set threshold alert values


Call Center	5	10	15	20
All				
Bolts Sales	1	2	5	10
Nuts Sales				

Double click an entry in the list to set overall threshold values or those for a specific call center. In the example below statistics columns have been added, some have been renamed from the default and threshold alerts have been configured.

Calls In Queue	Total Calls	Calls Answered	Total Missed Calls	Average Talk Time	Missed %	Busy Overflows
0	0	0	0	00:00	0.00	0
0	2	2	0	01:31	0.00	0
0	35	33	2	02:58	5.71	0
0	6	6	0	02:25	0.00	0
0	43	41	2	01:43	1.43	0

### 5.3 Joining & Leaving Queues

Right click any queue in the Personal Wallboard to toggle between Join and Leave queue. Queues that you are joined to have a green icon next to them. A red icon indicates that you are not joined to that queue.



### 5.4 Receiving ACD Calls

Inbound ACD calls will display the call center name, as configured in BroadWorks, in the “To” field. The “From” field will display the incoming CallerID [if not withheld] or the name of the caller if that can be matched from the Directory. Answer the call by lifting the IP phone handset, clicking Answer/Release call control button or double clicking the call in the Active Call Window.


Unity Agent: Jenna Wimshurst - Available (duration: 01:36:42)

File Messaging Tools Help

Unavailable Available Wrap-up **Answer** Dial Transfer Hold Conference Voicemail Recording Reports Settings


My Statistics										Overall Queue			
Name	Total Calls	Web Chats Answered	Answered Calls	Total Talk Time	Missed Calls	Average Talk Time	Emails Answered	Web Chats Received	Total Calls	Calls Answered	Total Missed Calls	Calls In Queue	Longest Wait Time
Kakapo Systems	0	0	0	00:00	0	00:00	0	0	0	0	0	1	00:00
Bolts Sales	0	0	0	00:00	0	00:00	0	0	0	0	0	0	00:00
Nuts Sales	0	0	0	00:00:00	0	00:00	0	0	0	0	0	1	00:00

Activity	From	To	Duration	Status
Queued				
Call	Natalie Maines (Salesforce Contact)	Bolts Sales	00:00	Ringing


Hang up the IP phone handset or click Release  to end the call.

### 5.5 Using Disposition Codes

Unity will expose ACD Disposition Codes as configured in BroadWorks, to agents within the Active Call Window. The user can enter one or more Disposition Codes by right clicking the active call and selecting from the context menu. Disposition Codes can be entered while the call is active, or immediately after, when the call has ended and before another call is answered. Only Disposition Codes configured for the queue that the agent has answered are displayed.




Disposition Codes can be assigned to the previous call either by selecting Assign disposition code  
 > Last call as above, or by right clicking in the Active Call Window post ACD call as below.




## 5.6 Auto Answer

Unity Agent optionally allows ACD calls to auto-answer when the agent is in the “Available” state. This is toggled on/off in Settings > Incoming Calls > Agent.



## 5.7 Supervisor Escalation

Unity Call Center Agent facilitates the BroadWorks call center escalation feature by allowing both standard and emergency call escalation. Both types of escalation can only be performed on call center calls and both inbound and outbound [DNIS] calls are supported. In either case, an agent can only escalate a call to a supervisor if that supervisor is currently supervising the agent in BroadWorks. If this is not the case the agent will be told [through the phone] that the supervisor is not a valid supervisor. However, Unity can be configured to display either only the supervisors that are supervising the agent, or all supervisors, as illustrated in the screenshot below.



### 5.7.1 Standard Escalation


Standard escalation is used when the agent needs to be given information or instruction from the supervisor without conferencing in the remote party. Typically, the agent will release the call to the supervisor and replay the information to the remote party. Unity allows the call to be escalated to a specific supervisor or to the first supervisor that is available. The agent's Unity client will automatically place the ACD call on hold, then dial the extension of the supervisor as an escalated call. This call will then appear as an escalated call in all center reports. Standard call policy/routing rules will be used when calling the supervisor, such as DND, call forwarding and hoteling guest etc. At any time, the agent can release the escalated call, or can transfer or conference both calls together if required.

### 5.7.2 Emergency Escalation


Emergency escalation is used to immediately conference a supervisor into the call with the remote party, therefore it relies on either the 3-Way Calling user service being assigned to the agent. When performing an emergency escalation, Unity will place any active calls on hold then dial the selected supervisor, or the first supervisor that is available.

### 5.7.3 Escalation via Active Call Window

To perform escalation, the agent right-clicks the call in the active call window, then either chooses the supervisor to escalate the call to:




Or escalates the call to the first available supervisor.



### 5.7.4 Escalation via Personal Wallboard

The agent can escalate a call center call by using the context menu displayed when right-clicking on the call center in the personal wallboard, as shown below. This assumes that Unity has logged in as the call center and is displaying statistics in the personal wallboard.




Please note that if the agent right-clicks on a different call center in the personal wallboard [to the one that the call was routed through] then the call escalation options will not be displayed.

## 5.8 Activating Outbound DNIS

If the agent is a member of BroadWorks call center premium queues, and the DNIS capability has been configured, then the user can select an outbound DNIS which will determine which outbound CallerID is presented when the agent makes external outbound calls.


Right click the Dial icon and mouse over “Change Outbound Number” at the bottom [the numbers above are a clickable list of last 10 numbers for redial]. The outbound DNIS that are available are presented. The currently selected outbound DNIS is ticked. This will affect all outbound calls until the outbound DNIS setting is changed, or set to none.




## 5.9 Personal Statistical Reports

Unity Agent provides access to the following agent reports:


1. Agent Activity Detail Report
2. Agent Activity Report
3. Agent Call By Skill report
4. Agent Call Detail Report
5. Agent Call Report
6. Agent Duration by Skill Report
7. Agent Duration Report
8. Agent Sign-In/Sign-Out Report

To access these reports, click the Reports button  or select Tools > Call Centers > Report Viewer from the menu. Specify the reporting period, click Tools > Call Centre > Report Viewer. From the Report Viewer interface [shown below] select the desired report and reporting period.




## 5.10 Pre-configuration of ACD State

Unity Agent offers a cascading hierarchy of agent availability settings that control the agent's join and ACD status depending on the status of the host computer. This is in Settings > Services > Incoming Calls > Agent.





In addition, the ACD state can be configured for computer startup and unlock state, postcall state and desktop locked state.




## 6 CALL CONTROL


---

All calls are managed through the call control buttons at the top of the application. These buttons will change depending on the state of the selected call, or the only call if there is only one call in the Active Call Window. For example, the Release  and Hold/Retrieve  buttons toggle as only one of these options will be valid at any time. When an inbound call is ringing Answer becomes the valid option. Once the call is active the icon will toggle to Release as hanging up is the only valid option.

### 6.1 Making a Call


#### 6.1.1 Using the Dial Window

Click the Dial button  to bring up the Dial dialogue box, as shown below. Using the computer keypad enter the desired number and press Enter or click OK to make the call. The desk telephone will default to using hands-free speakerphone. If the telephone does not support speakerphone, you will need to lift the handset when the call is answered.



#### 6.1.2 Using the Contacts Panel

Double click a user icon or right click and select “Call extension”



#### 6.1.3 Drag and Drop

Right click a user icon on the Contacts panel and drag the icon up to the Active Call Window. This will open a call to that user. Calls can also be dragged from the Active Call Window onto a call center to perform a blind transfer. Calls dragged onto a monitored user will either be blind transferred or present options depending on the user preferences in Settings and whether the monitored user is engaged or not. For engaged contacts, park, camp-on and transfer to voicemail are available. For available contacts transfer to extension, transfer to mobile, transfer to voicemail or present call hold, camp on and transfer are available.


### 6.1.4 Using Directory Search

Enter the search field in the Contacts panel to dynamically search all internal users and speed dials. Either right click and select “Call extension” or right-click and drag the icon into the Active Call Window to make the call.


### 6.1.4 Dialing from the clipboard

Any number that is copied to the Windows clipboard, (highlight the telephone number, right click, then clicking copy) this will cause a popup toast above the system tray with the option to call the number. Click the toast notification to make the call. This feature can be enabled/disabled in Settings. When a number is copied to the clipboard, Unity can show a prompt to the user which appears over all applications, rather than show a toast notification. This can be configured through Settings>Settings tab>Clipboard Integration.

## 6.2 Answer a Call

When Unity displays an inbound call, click the Answer icon  or double click the call in the Active Call Window to answer the call. Your desk telephone will now be on hands-free speakerphone, if it supports this feature with Unity. If there is an active call in progress, you will need to click the new inbound call in the Active Call Window before clicking Answer, this will automatically place the first call on Hold. Please note that answering a call by lifting the handset on the desk phone will have the same effect as clicking Answer in Unity.


## 6.3 End a Call

Click the Release button  to end the currently selected call. If there are multiple calls in the Active Call Window, make sure you select the right call before clicking Release.


Note: Replacing the telephone handset will also end the call, which will then be removed from the Active Call Window.

## 6.3 Redial

You can also right-click the Dial button to see a list of the last 10 dialed numbers. Simply click on an entry to dial the party, as shown below.



## 6.4 Send Call to Voicemail

To send an inbound caller directly to your voicemail click the Voicemail button .


Please note that if voicemail is not assigned or is disabled, the button will still be visible but inactive.

### 6.4.1 Retrieving Voicemail Messages via VoiceMail Button

When no calls are currently selected, clicking the Voicemail button will dial the user into their voicemail. The phone will default to hands-free speaker phone if it has this capability

### 6.4.2 Retrieving Voicemail Messages via Voicemail tab

Clicking into the Voicemail tab will display a list of voice messages with the most recent at the top. Double click an entry to play through the PC's default media player. Right click to save locally or delete. In order for the Voicemail tab to appear, Agent must be configured for "Use unified messaging" and "Show visual voicemail tab" in Voicemail settings as below.




## 6.5 Transferring a Call

There are two ways to transfer a call; Announced Transfer, where you introduce the call to the receiving party before putting the call through, and Blind Transfer, where you transfer the caller

directly to a recipient without introducing the call. Please note that calls can be transferred both to internal users and external contacts.


### 6.5.1 Announced Transfer

Receive and answer an inbound call. Make a new call to the desired destination extension or number as described Make a Call above. This will automatically place the first caller on Hold and will open a new call in the Active Call Window. Once the called party answers, click Transfer  and select the context menu option to transfer both calling parties together. Both calls will now disappear from the Active Call Window.

Note: The user is not limiting to transferring received calls. They can make two outbound calls and then use transfer to “bridge” them together.

Calls can also be transferred together by dragging one call on top of another within the Active Call List

#### Example 1 – Transfer with two live calls




Name	Total Calls	Answered Calls	Missed Calls	Total Talk Time	Average Talk Time	Total Calls
Nuts Sales	0	0	0	00:00:00	00:00	0
Bolts Sales	4	4	0	00:01:09	00:18	4
	4	4	0	00:01:09	00:09	4

From	To	Duration
Jenna Wimshurst	03456040626	00:19
Jenna Wimshurst	01268508018	00:05

#### Example 2 – Transfer with four live calls



Name	Total Calls	Answered Calls	Missed Calls	Total Talk Time	Average Talk Time	Total Calls
Nuts Sales	0	0	0	00:00		
Bolts Sales	4	4	0	00:01:09	00:18	4
	4	4	0	00:01:09	00:09	4


  

From	To	Duration
Jenna Wimshurst	03456040626	01:37
Jenna Wimshurst	01268508018	01:24
Jenna Wimshurst	03459758758	00:17
Jenna Wimshurst	03457203040	00:02

### 6.5.1.1 Warm Transfer

Unity Agent allows you to warm transfer a call by right clicking the user you want to transfer the call to and selecting “warm transfer” from the context menu. This will then put the original caller


on hold and dial the selected number. When ready, click the transfer button in the call center control options panel and the two calls will be transferred, automatically disappearing from your active call window.




## 6.5.2 Blind Transfer


### 6.5.2.1 Using Contacts Panel Drag and Drop

Unity Agent can be configured to automatically blind transfer a call by dragging the call from the Active Call Window and dropping it on a user icon or number icon in the Contacts panel, or dropping it onto a call center queue [if agent is configured as an agent with call center queues]. Note: Unity can be configured to display a menu when dropping a call onto a user icon. If no menu options are selected the blind transfer is performed. If menu options are selected, click “Transfer call to extension” to also perform blind transfer. For more information on Drag & drop refer to section 8.




### 6.5.2.2 Using Transfer Button

Once on a call click the Transfer call control button . In the Transfer window enter the destination and click OK.



### 6.5.2.3 Using Right Click

While on an active call right click the recipient icon or number in the Contacts panel or Search. Select “Transfer call to extension” to blind transfer the call.




## 6.5.3 Transfer to Voicemail

The option to Transfer to voicemail is valid only for internal company users that have Voicemail assigned and activated.


### 6.5.3.1 Using Contacts Panel Right Click - Voicemail

While on an active call, right click a user in the User Status list and select “Transfer to voicemail”. This will send the selected call directly to the destination extension voicemail without introducing ringing.



### 6.5.3.2 Using Drag and Drop


If configured, Unity will display “Transfer to voicemail” in the list when an active call is dragged onto the destination user icon in the Contacts panel. For more information, refer to section 8.



## 6.5.4 Transfer to Mobile

If the destination user has a mobile number entered as part of their profile in BroadWorks, you have the option to right click and select either Dial Mobile [to perform an announced transfer] or Transfer Call to Mobile [to perform blind transfer].

#### 6.5.4.1 Using Contacts Panel Right Click - Mobile



Right click the desired user in the Contacts panel. To announce the call, click Dial Mobile. Once the recipient answers click Transfer  and select the context menu option to transfer the calls together.

To blind transfer the call without introduction click Transfer call to mobile.

#### 6.5.4.2 Using Drag and Drop


If configured, Unity will display “Transfer to mobile” in the list when an active call is dragged onto the destination user icon in the Contacts panel. For more information refer to section 8.

### 6.6 Call Hold/Retrieve


The Hold/Retrieve   function toggles depending on the status of the currently selected call. Hold is only available for an active call while Retrieve is only a valid option for a call currently on Hold. When a call is on Hold, the blue Hold icon is shown in miniature to the left of the call in the Active Call Window and the status is On Hold, as shown below.

From	To	Duration	Status
 Jenna Wimshurst	Sasha Gorb	00:04	On hold

#### 6.6.1 Placing a Call on Hold

To place a current active call on Hold, press the red Hold button . The call status will now show as on hold in the Active Call Window and there will be an On Hold icon alongside the call.

#### 6.6.2 Retrieving a Held Call

Click the held call in the Active Call Window to select it. Click the Retrieve button  to take the call off hold, you can also double click the call to retrieve it. Please note that any other active calls will be placed on hold before the selected call is retrieved, meaning you can toggle between call by double-clicking them in the Active Call Window.

### 6.7 Conference Calling

A conference call can be established with any combination of internal and external numbers. The total number of parties that can be supported is determined by service assignment. The Three-Way Calling user service supports conference calls with two other parties only while the ayW Calling user service supports conference calls with more participants.

### 6.7.1 Starting a Conference Call

Once an active call is established [that you have either made or received] call a second person.

You can do this by clicking the Dial button or double clicking a user in the Contacts panel or Search, or Call Log lists. Making this call will automatically place the first caller on Hold.

Once the second party has answered the call, click the Conference button and a new conference will be created between you and the other two parties. This is represented in the Active Call Window as shown below:

From	To	Duration	Status
 Sasha Gorb	Jenna Wimshurst	00:15	Active (conference)/Not recording
 Jenna Wimshurst	01268508018	00:02	Active (conference)/Not recording

Selecting either call and clicking Hold will place the conference call on hold, during which time the other callers can still talk to each other.

From	To	Duration	Status
 Sasha Gorb	Jenna Wimshurst	00:36	On hold (conference)
 Jenna Wimshurst	01268508018	00:23	On hold (conference)

### 6.7.2 Ending a Conference Call

To remove a caller from the conference call but continue speaking to the other caller[s], simply

select the call to release in the Active Call Window and click the Release button as you would normally. This will release the selected party and will show only the remaining party[s] in the Active Call Window.


To end a conference call but leave the two remote parties in conversation with each other, click the Transfer button and select the “leave conference” menu option, as shown below.



## 7 ACTIVE CALL WINDOW

The Active Call Window gives visual representation of the status of all calls the user receives or is currently managing.

## 7.1 Window Layout

From	To	Duration	Status
 Jenna Wimshurst	03456040626	00:18	On hold
Jenna Wimshurst	Sasha Gorb	00:00	Ringling

**From** – This field will display the incoming CallerID or the name if it is matched in the Group/Enterprise directory, Personal Contacts or Outlook Contacts.

**To** – This field displays the name of the user, hunt group or call center that has been called ensuring the call can be answered appropriately.

**Duration** – This displays the total time elapsed since the call was first answered. The timer does not restart when the call is placed on hold.

**Status** – This shows the Ringing/Active on On Hold status of each call.

## Calls In Queue

Agents can optionally see all calls in queue for the Call Centers they are joined to, as shown below.

From	To	Duration	Status
Hot Desk 3 - 9103	Bolts Sales	01:48	Queued at position 1
Charlotte Quartly	Bolts Sales	01:25	Queued at position 2


## 7.2 Managing Multiple Calls

To manage a particular call, first select it by clicking it in the Active Call Window. If there is only one call in the list it will be selected automatically. You can then use the call control buttons to perform different actions on the call. There is no limit to the number of calls that can be displayed in the Active Call Window, this is limited by the number of simultaneous calls allowed and if the Call Waiting user service is assigned and active.

You can also double-click an incoming [unanswered] call to answer it, or to retrieve it if currently on hold.


## 7.3 Resizing the Active Call Window

The bottom border of the Active Call Window can be dragged down to display as many or as few calls as necessary. Unity will save these dimensions when closed. Unity can automatically resize itself to include all calls, as well as group waiting and queued [if applicable] calls together, as shown below.




## 7.4 Assigning an Account Code

Account codes can be assigned to a call through the Active Call Window as shown below, please note that Unity must place the call on hold in order to assign the account code, then will attempt to retrieve the call although this isn't always possible in which case the user must retrieve the call using the phone.





Unity will display a notification to indicate that the call was successfully assigned to the account code:



## 8 DRAG AND DROP


Many common call handling actions can be performed with drag and drop, as well as right click and call control buttons.

## 8.1 Make a Call to a User or Number

Drag a user icon  or a speed dial shortcut icon  from the Contacts panel up into the Active Call Window to make a new call to the selected user or number.

## 8.2 Transferring a Call to a User

Drag a live call onto a user to either perform blind transfer, or to populate a drop list with call handling options. The drag and drop behavior for this action is configured in Settings as shown below.




## 8.3 Make a Call to a Call Center Queue

When agent is configured as an agent, drag a call center queue from the Personal Wallboard to the Active Call Window to make a call to that call center.

## 8.4 Transferring a Call to a Call Center Queue

If agent is configured as an agent, you can drag a current call in the Active Call Window up and drop it on a Call Center in the Personal Wallboard. This will blind transfer the call to the call center.

## 8.5 Send to Voicemail



Dragging an unanswered call from the Active Call Window onto the Voicemail button  will blind transfer the incoming call to your voicemail.

## 8.6 Call Control

Dragging a call over the Hold/Retrieve, Answer/Release, Transfer or park buttons will perform that action on the selected call.

## 8.7 Send New Instant Message

Drag a user to the docked IM window to the right of the Contacts panel to send an IM to that user. This requires that the “Always show docked panel” field is ticked in Settings > Instant Messaging and Presence.



See also section 10 on Instant Messaging.


### 8.7.1 Add Participant to Existing IM Session

Drag a user icon onto an existing IM and choose “Add to the conversation”




## 8.7.2 Transfer Call to IM Participant

Drag a call from the Active Call Window onto an IM session in the Docked IM Window and you will see a prompt to transfer the call. This is particularly useful if you want to check the recipient's availability before you transfer.



When dropping a call onto a multi-party IM session you will be prompted where to transfer the call.




## 9 CONTACTS PANEL [BUSY LAMP FIELD]

The Contacts tab gives a visual indication of the status of users [within the group/enterprise] that are currently being monitored. A maximum of 30 users can be displayed. Double clicking a monitored user will call them and right clicking will bring up a dynamic options menu.

### 9.1 Contact Panel Display Options

There are three different views available, as outlined below. Right-click anywhere in the Contacts panel and select Appearance list to change the view.




### 9.1.1 Details View

This view provides by far the greatest amount of detail, but requires more space [although the list can be shortened in which case scrollbars will automatically appear].


Contacts   Activity Logs   Abandoned Calls   Voicemail				
My status: available in office				
Name	Phone	ACD State	Status	
✓ Chris Tutt	020828812	Sign-Out		
✓ Cindy Baker	020828812			
✓ Colin Wardle	020828812	Sign-Out		
✗ Dave Baker	020828812	Available	Talking to +447717580512 - 20:22 / In a meeting	
✓ David Higgins	020828812	Sign-In		
✓ Dean Thompson	020828812	Sign-In		
✗ Ed Thrus	020828812	Sign-In	Currently away	
✓ Gopikrishnan V	8332	Available		
✓ Iain Sin	020828812	Sign-Out		
✓ Krysta Swiatek	020828812	Available		
✓ Lee Hous	020828812	Sign-In		
✗ Lewis Marcan	020828812	Available	Talking to Conference Bridge - 18:35 / Currently busy	
✗ Paul Farrant	020828812	Available	Talking to Alastair Brown - 02:00	
✓ Steve Tutt	020828812	Unavailable - WebChat		
✓ Steve Wardle	020828812	Unavailable - Comfort Break	In a meeting until 3pm	
✓ Vas Koria	020828812	Available		

With this view the sort order for each column can be set, which is saved when Unity is closed. You can also configure Unity to display or hide the extension, department, ACD state and call duration columns.




### 9.1.2 List View

This option will display all users in a list.




### 9.1.3 Small Icon View

This view combines a simplified look and space reduction.




### 9.1.4 Tile View

This view is similar to Icon view but uses more white space to provide a cleaner look.



In both the Icon and Tile views, hovering the mouse over the image will provide more information about the monitored user, for example their service configuration:



## 9.2 User Icons

There are four main user icons states shown in the Contacts panel, regardless of the view chosen.

	Available	The monitored user extension is on hook
	Ringing	The monitored user extension is ringing
	Engaged	The user is on the phone
	Do Not Disturb	The user has selected DND or Unavailable profile

### 9.2.1 User Icon Engaged Tool Tip

Hovering your mouse over an engaged or DND icon will reveal more information about their current state, if available. For engaged users this will include the name or number of the party they are engaged to and the duration off the current call as below [this feature can be disabled for privacy reasons].




### 9.2.2 Instant Messaging Availability

Regardless of a user's Available/Ringing/Engaged/DND state, if they currently have any version of Unity open they will be available for instant messaging. This is shown by the envelope at bottom right of the user icon, as per the following examples.


	Ringing. Unity open and available for IM
	DND/Unavailable profile. Unity open and available for IM
	Engaged. Unity open and available for IM
	Available/on-hook. Unity open and available for IM

## 9.3 Managing Monitored Users in the Contacts Panel


The Contacts panel will display 30 users. In the Contacts panel right click anywhere and click "Manage user list". This will allow you to choose which users to display.



You will then be able to move users or departments between the lists either by double-clicking them or using the arrow button. All users in the right-side list will be monitored in the Contacts panel. This list is saved when Unity is closed.



The box at top left will dynamically search the group directory.



## 9.5 Performing Call Control Actions in the Contacts Panel

There are many call control functions that can be performed by right-clicking a monitored user in the main Contacts panel or Search. The menu options displayed will dynamically change to only show those available depending on the state of the monitored user and/or the state of the selected call in the Active Call Window [if there is one]. For example, “Transfer to voicemail” will not be available if the user does not have the voicemail service assigned and “Camp call on extension” will not be available unless there is a live call selected in the Active Call Window.

### 9.5.1 Call Extension

Selecting “Call extension” will open a new call to that user in the same way that double clicking the user icon would. Any current call will automatically be placed on hold. This can be used to make an announced transfer as opposed to a blind transfer using the “Transfer call” commands further down the menu.

### 9.5.2 Answer This Call [Call Pick-Up]

This will perform call pick-up and will pull the call to the ringing Agent user.

*Feature Dependency:*

- I. Monitored user must be ringing [orange icon]
- II. Agent and monitored users must be in the same pick-up group

### 9.5.3 Park Call on Extension


Will park the call on the monitored user's extension park slot.

*Feature Dependency*

- I. Must have a live call

#### 9.5.3.1 Retrieving Parked Calls

Once a call has been parked onto a user's extension, their Unity will display a "Pickup Call" icon and a toast pop up window will appear. In order for the user to retrieve the parked call they simply need to click either the "P" or the toast pop up. If the call is not retrieved it will be redirected back to the original user who parked the call.




### 9.5.4 Camp Call on Extension

Will camp the call onto the engaged monitored user. When the user goes back on-hook the camped call will be delivered and their phone will start ringing. If the user does not go back on-hook before the camp timer expires the call will return to the Agent user.

*Feature Dependency*

- I. Must have a live call in the Active Call Window
- II. Must be enabled in Settings > Call Transfer as below

The Camp Call option will only be available if activated in Settings > Call Control > Call Transfer as below.



## 9.5.6 Call Mobile

Places call to mobile. Any live call placed on hold.

*Feature Dependency:*

The monitored user must have their mobile number entered in BWKS

## 9.5.7 Transfer Call to Mobile

Performs blind transfer call to monitored users mobile.

*Feature Dependency:*

- I. The destination user must have their mobile number entered in BWKS
- II. Must have a live call

## 9.5.8 Transfer Call to VoiceMail

Performs blind transfer to the destination user's voicemail.

*Feature Dependency:*


- I. The destination user must have voicemail service assigned
- II. Must have a live call

## 9.5.9 Barge into This Call

Makes an immediate three-way conference call with the Agent user, the monitored user and the third party the monitored user is talking to. All parties will be able to talk and hear each other. When attempting to barge into a call, if the phone plays a “number doesn’t exist” tone then this means the monitored user cannot be barged into, because they have the Barge-In Exempt service assigned and activated. Only users without this service active can be barged into.

The Active Call Window will display like a normal conference call, as below, and the Agent user can Hold/Retrieve the same as for a conference call.

From	To	Duration	Status
 Sasha Gorb	Jenna Wimshurst	00:15	Active (conference)/Not recording
 Jenna Wimshurst	01268508018	00:02	Active (conference)/Not recording

Please note that when leaving a call that you barged into, you must transfer the call parties together in order to leave the conference without ending the original call. To do this either drag one call on top of the other in the Active Call List, or press Transfer  then select the option to leave the conference, as shown below.




#### *Feature Dependency:*

- I. The Agent user must have directed call pick-up with barge-in service assigned
- II. Monitored user must be engaged on a call
- III. The monitored user must not have the barge in Exempt service active

### 9.5.10 Call Extension When Available

Places an alert on the engaged monitored user. When they become free a dialogue box prompts the Agent user and allows them to open the call back.



#### *Feature Dependency:*


- I. Monitored user must be engaged on a call

### 9.5.11 View User Details

Performs a lookup on the user's details as entered in BWKS. This includes their phone number, mobile and email address.



### 9.5.11.1 Adding Audio Alerts to Monitored Users

The “View user details” box also allows a wav file to be specified that will be played when the monitored user receives a call. Click the  icon to select the wav file then click OK. This feature is useful in Manager/Secretary scenarios where the Agent user is screening calls. When the audio alert plays that is the reminder for the user to perform call pick-up.


### 9.5.12 Send Email


This will open a new email window in the default Email application. The user must have the email filed populated against their name in BWKS.

*Feature Dependency:*

- I. The recipient user must have their email address entered in the system

### 9.5.13 Answer This Call [Call Pick-Up]

When monitored users are ringing their icon in Contacts becomes orange . To perform pick-up and answer the call right click the icon and select “Answer this call”. This option is only displayed when right clicking a ringing user.



*Feature Dependency:*









- I. The Agent user and the monitored user must be the same pickup group or the Agent user must have the “Directed Call Pick-Up” service assigned.

## 10. INSTANT MESSAGING

Instant messages can be sent and received between any Unity app [Reception, Desktop, Agent, or Supervisor]. Messages sent to offline user [those that do not have an instance of Unity open] can be stored and delivered when the recipient next opens Unity.

### 10.1 Online/Offline Indicator

A person that is running an instance of Unity, and therefore available to send an online IM to is indicated with a small envelope on their user icon. This applies across all the available, engaged, ringing and DND states as shown below.


State	Online [Unity Open]	Offline [Unity Closed]
Available		
Ringing		
Engaged		
DND/unavailable profile		

### 10.2 Docking the IM Window


Instant Messages can be displayed in the Docked IM Window or as separate dialogue boxes for each individual IM thread. If the docked window is used IMs can be initiated via drag and drop and new IM windows will not pop over other applications.



Docking the IM window is specified in Settings > Settings > Instant Messaging and Presence > “Show instant messages in docked panel”. Individual IM messages can still be undocked and redocked as required.




### 10.3 Undocking and Redocking IM sessions

You can undock an IM message by clicking the  “Expand conversation to separate window” button. The IM session will now be a standalone window.

#### Docked IM



Click the  “Dock conversation in main window” button to pull the IM session back into the docked panel in the main Agent interface.

#### Undocked IM




## 10.4 Sending an Instant Message

Send an instant message either by right clicking a user icon in Contacts panel or Search and selecting “Instant Message” from the drop list, or by dragging a user icon into the docked IM panel. Alternatively, you can select Messaging > Start Conversation from the top menu bar.



You can then select the users to include in the IM conversation. Please note that only online users will be displayed in the lists. The left list contains all online users, to include them in the IM conversation move them into the right list either by double-clicking the entry or using the arrow button.




## 10.5 Overview of IM Window

The upper part of the IM window will scroll to display the most recent comment. Type your comment in the bottom window and press Enter or click the  envelope at bottom right.


### IM Window - Docked




## IM Window – Undocked



## 10.6 Adding Participants to an Existing IM Session

When an IM conversation is in the Docked IM panel you can drag a user icon from the Contacts Panel or Search and drop them on the IM window to add them to the conversation. When the IM Window is undocked you click the  Search icon and select participants to add to the conversation, as below.



## 10.7 Sending Contact Directory Numbers


To send another user a number from your Directory right click in the bottom panel where you enter text. Mouse over to see your Directory entries and select the appropriate number.

### Feature Dependency:

- II. The recipient user must have their email address entered in the system
- III. The Agent user must have their outlook client open and they must have full sharing Permissions to see the monitored user's Calendar in Outlook

## 10.8 IM Notification Settings

All notification options for IMs, including sound and popup notifications can be found in the settings under Instant messaging & Presence.



Selecting the 'Show popup notification until closed' will keep the IM popup on the screen until it has been closed or clicked.




## 10.9 Send IMs to Offline Users

Even when a user is offline, Unity will allow you to send them an instant message which will then be queued and will appear the next time the user is online.

### 10.9.1 Logging IM Sessions

You will find the Instant Messaging and presence logging options in the Settings tab. Here you will be able to configure how IMs are saved, what file type they are (CSV or HTML) and where they are saved, for example, you may want to save IM conversations on your server rather than on the agent's local computer.




## 10.10 XMPP Integration

Unity provides seamless integration with XMPP in order for Unity users to share instant messaging and presence (IM&P) functionality with UC-One clients. All instant messages are displayed and managed to the user as a docked or undocked IM conversation, regardless of the IM&P platform being used. Only online users in Unity can participate in group chats, group chat is not currently supported with XMPP.


### 10.10.1 XMPP Authentication

Unity is unable to extract the XMPP password from the VoIP platform, meaning it must be reset from within Unity. This functionality relies on the Integrated IM&P service being assigned to the Agent, although no other UC-One related service need be assigned.

In order to set the XMPP password go into Settings and click on the “XMPP > Change Password” item as shown below. You can see the current XMPP status is offline.




Once the password has been entered you must click the OK button to save the password, before moving to any other panels in settings. Please note that the XMPP password should not be the same as the password used to first log into Unity. You will be notified once the password has been changed and the XMPP status changed to online, as shown below.




## 10.10.2 Managing XMPP Subscriptions

To subscribe to XMPP presence for a monitored user (meaning the Agent will receive real-time updates as the monitored user changes their presence in UC-One) simply right-click the user and select “Add XMPP presence”, as shown here. If already subscribed, then right-click the user to remove XMPP presence.



Unity will show the unavailable, busy etc status of the user, as well as any status message manually entered in UC-One, as illustrated below.



✓	Steve Tutt	02082881251	
✗	Steve Wardle	02082881245	In a meeting until 3pm / Currently away

Please note that at present XMPP is only used by Unity to communicate with UC-One clients.

Unity can be configured to automatically subscribe to all monitored user's XMPP presence, as shown here. However, this may result in the buddy/contact list in UC-One becoming very large so should only be activated if the Agent doesn't often refer to the buddy list.

Unity can also be configured to automatically accept subscription requests from other users, if this setting is not activated then whenever a user subscribes to the Agent's XMPP presence a prompt will be displayed, as below.

**XMPP Login Details**

Status  
Online

Login ID  
442082881248@voice2000.eu.bc.im

Password  
\*\*\*\*\*

☐ Automatically accept subscription requests

☐ Automatically send subscription requests

When a contact is online in Unity IM&P and XMPP  
Use Unity IM&P



**XMPP Login Details**

Status  
Online

Login ID  
442082881248@voice2000.eu.bc.im

Password  
\*\*\*\*\*

☐ Automatically accept subscription requests

☐ Automatically send subscription requests

When a contact is online in Unity IM&P and XMPP  
Use Unity IM&P  
Use Unity IM&P  
Use Both


Unity can be configured to automatically generate an XMPP password the first time it is loaded, this is a branding property that is set in the Unity Client branding portal. In this case Unity will save the randomly generated password in Broadworks and also in the registry, from where it will be used whenever Unity is next started. When the password is reset in Broadworks it will automatically be updated in the device configuration file for UC-One, if in use. Furthermore, if UC-One is currently in use this will not impact the existing XMPP registration, therefore there is no impact on UC-One.

### 10.10.3 Instant Message Priority

Because a monitored user could be running Unity and UC-One, that user could be available to receive instant messages using either client, or both. In these situations, Unity can be configured to prioritized one IM platform over the other, as shown below.


Options are to only send the instant message using only Unity IM&P meaning the instant message will not be received by UC-One, to only send using XMPP meaning the monitored user's Unity client will not receive the message, or to send through both messaging protocols meaning both clients will receive any instant messages sent from Unity. The last option is the default and is recommended in most scenarios.

### 10.10.4 Configuration




## 11 PERSONAL DIRECTORY


---

The Personal Directory is a repository on BroadWorks for each user to store personal speed dials. Using this feature in Unity will populate the directory on the host BroadWorks platform. Once numbers have been entered they are available in the Search panel or can be pinned to the main Contacts Panel. A Personal Directory entry is shown by a  icon. Double clicking the icon will make a call to the Directory number. The Personal Directory menu is available when right clicking a monitored user or in the Contacts panel.

### Personal Directory – Right click in Contacts




### Personal Directory – Right click on monitored user




### 11.1 Add New Entry

Enter the Name and Number and click Ok


A screenshot of a dialog box titled 'Add Personal Directory Entry'. It has two input fields: 'Name' with the text 'Derek Lynch' and 'Phone' with the text '07976'. At the bottom, there are two buttons: 'Cancel' (with a red X icon) and 'OK' (with a green checkmark icon).

If the number specified is already in the Directory the user will be alerted as below.




## 11.2 Edit Entry

Use the Search field in Contacts to locate the entry. You can search by either Name or Number. Right click the Entry and select “Edit”.




## 11.3 Remove Entry

Use the Search field in Contacts to locate the entry. You can search by either Name or Number. Right click the Entry and select “Remove”.




## 11.4 Dialing Directory Entry

Locate the entry either on the Contacts panel or Search. Drag the entry into the Active Call Window or double click to make a call, or right click the entry and click “Call number”.



## 11.5 Import Personal Directory

Agent will allow the user to import a .csv file of directory entries, provided they are in “name, number” format. Right click in the Contacts panel, select “Personal directory > “Import” and then browse to the location of the csv.




## 11.6 Export Personal Directory

To export Personal Directory entries right click in Contacts and select Personal directory > “export”. You will be prompted to save the file locally. The format is csv and the default file name is PersonalDirectory.csv



Choose save location on local PC.

The format of the csv is Name and then Number. Note the example below is edited for privacy.

A screenshot of a Microsoft Excel spreadsheet. The spreadsheet has columns A, B, and C. Column A contains names, column B is empty, and column C contains numbers. The data is as follows:

	A	B	C
1	Alex		260208
2	Alli		403004
3	And		670809
4	And		022005
5	And		101333
6	Ben		627966
7	Cha		797620
8	Chri		470090
9	Clai		454476
10	Dad		344175
11	Dad		300005
12	Feis		269300
13	Fras		586676
14	Garr		843921
15	Grai		040086

## 12 CONTACT SEARCH DIRECTORIES

The Contact Search field combines all BroadWorks and Outlook Contacts directories to create a central search repository. The BroadWorks directories include the Common Phone List [system speed dials], the Agent user's own Personal Directory entries, and the Group Directory which includes all the other users in the group as well as hunt groups, auto attendants and call centers. Unity can also integrate with third party LDAP [including Microsoft Active Directory] and SQL directories as well as integrating with CRM systems.

Please see your Administrator for a separate guide on using CRM integration.


Directory Owner	Directory Type	Entry Type
<b>BroadSoft</b>	Group Directory	All other users for BLF presence as well as hunt groups and auto attendants
<b>BroadSoft</b>	Common Phone List	Speed dials entries at the Group level
<b>BroadSoft</b>	Personal Directory	The user's own personal speed dial entries
<b>Outlook</b>	Personal Contacts [private folder]	The user's own Outlook Contacts
<b>Outlook</b>	Group Contacts [public folder]	The shared Outlook Contacts at the Outlook group level
<b>Third Party</b>	SQL	External SQL Directory
<b>Third Party</b>	LDAP	External LDAP Directory

### 12.1 Loading Directories

Unity will load all directory entries into Contact Search on start. If users are added to the BroadWorks Group Directory while Unity is running, they will not be visible until Unity has restarted. Personal directory entries the user adds will be available to use immediately without restarting.

### 12.2 Contact Search Results Layout

To perform a search type characters or numbers in the Search field and Agent will start dynamically populating a list of matching entries across all directories. The list will narrow as more characters or numbers are entered. Clearing the Search box and returning to the main Contacts panel can be achieved by clicking again in the Search field [provided "Clear the search box when activated" is enabled in Settings as outlined in the section below.




Search results will display each number for a contact as a separate line. Drag or double click the entry to make a call or right click to select a call action from the context menu.

Icons represent external numbers or system resources such as hunt groups for which presence information cannot be displayed. It is also possible to search on department name to list all users of matching departments.


## 12.3 Contact Search Settings

Preferences for Search can be configured in Settings > Unity Settings > Contact Search. The order of search results can also be changed to display internal extension users first and the “Include department name in search” as shown above, can be toggled.




### 12.3.1 Listing Directories

Right-click the search box in the Contact list to view all directories available in Unity, then select the directory to load those contacts in the list, as below.




## 12.4 Configuring Outlook Contacts Preferences


The Outlook directories are both public and private folders and is configurable in Settings > Outlook Integration as below.



## 12.5 Third Party Directories


When searching BroadWorks and Outlook directories, Unity will dynamically match entries as keys are typed. For third party LDAP and SQL directories, because these are not loaded into Unity but polled each time a search request is made, search results are not listed until the Agent user has entered three characters and hit enter or clicked Search .

Unity includes a wizard to connect to third party SQL and LDAP directories. Go to Settings to add, edit and remove custom directories, as shown below.



## 12.6 Desktop Integration

Go into Settings > Settings tab > Desktop Integration, as below.




Unity must be configured with the folder location where the file is to be written, you can also specify whether to use the remote number as the filename (for example 02082881248.txt) or to include the remote number in a text file with whatever naming convention you require. Lastly you should instruct Unity when to create the file, for example only when receiving [call center] calls. Please note that Unity will only create the file for an inbound call when the user has answered it.

When you click OK to save, Unity will attempt to create a file called test.txt in the specified folder, then to delete it, which is to test that appropriate folder permissions have been applied. If this fails, Unity will alert the user and the settings will not be saved.

## 13 CALL LOGS

The Call Logs tab displays Missed, Received and Dialed Calls with a date and time stamp showing the most recent call at the top. Up to 20 numbers are listed unless the Enhanced Call logs service is assigned to the Agent user in BroadWorks. Calls to the Agent user DID as well as hunt group and call center calls that have reached the Agent user are shown.

Contacts   Call Logs   Voicemail   Abandoned Calls		
<input checked="" type="radio"/> Missed calls <input type="radio"/> Received calls <input type="radio"/> Dialed calls		
Call Date	Phone Number	Name
11/08/2016 16:01:38	1248	Chris Tutt
11/08/2016 12:37:31	0139	0139
08/08/2016 16:30:58	0208	0208
07/08/2016 18:34:40	0002	Andrew Smith
07/08/2016 18:34:20	0002	Andrew Smith

Drag or double click an entry to make a call to that number. Call logs can be exported as a csv file, either individually or together, but clicked the  Export button.